

Entity 1

Gel Technology



SCULPTING ON A FORM

featuring

UV White Gel ~ Building Techniques

PREFORM PREP STEPS

FORM FIT

1. While holding both sides of the **Clear** Entity Sculpting Form, gently roll back and forth to begin shaping form into desired "C" curve. Place form securely against the free edge of the natural nail. Create the "C" curve and secure by pressing form along lateral walls and pinching the front tabs. Secure the rear tab by pinching together or opening up to accommodate finger size. View fit of the form by looking down the barrel. To avoid seepage the form should fit tightly against the free edge of the natural nail.
2. Apply a very thin coat of Nu Bond non-acid primer. Dip brush and press against the edge of the bottle to drain. Starting with the thumb apply one coat to each nail be sure to avoid contact with the surrounding skin and form. Apply to one hand at a time to avoid contamination.

PRODUCT APPLICATION

3. Apply one thin base layer of Clear, Pink or Nudite Pink over the entire length of the enhancement and cure for 2-3 minutes. This thin layer will reduce the possibility of burning and allow for better workability of the White Gel application.
4. To build your free edge start at the upper corner of where you wish to begin your smile line; gently touch the White gel to that spot and string/drag the product down towards what will be the center and lowest part of your smile line. Repeat this process on the opposite side of the nail.
5. Gently brush the product from the smile line to the free edge making sure to cap the free edge. Applying the White gel layer too thick or in multiple layers can cause under curing.

6. To clean and define the smile line; dip your brush into the Natural Nail Prep and clean on a Brush Wipe. Then use it to carefully define and smooth out the smile line. Cure for 3 minutes.

**** At any point while applying gel finger to finger you may freeze the product into place by placing in the UV Lamp for 10 seconds; be sure to complete the final cure for a full 2-3 minutes****

7. Apply one layer of clear, Pink or Nudite pink gel and cure for 2-3 minutes. On a new set, flat or ski jump nails additional layers may be required to build a proper apex for additional strength. If using Pink or Nudite Pink be sure not to pull gel over the white free edge. Each layer must be cured for 2-3 minutes. Dip your brush into Natural Nail Prep and clean on a Brush Wipe in between colors or when needed. Apply a coat of clear over the entire surface and cure for 2-3 minutes.

Remove the form, remove the sticky layer with Natural Nail Prep and file the nail into your desired final shape using the techniques in the **Shape and Perfect** section.

SEAL and PROTECT

8. Apply a thin layer of UV Gel Top Coat and cure for 2 minutes.
9. Finish the service by massaging Cuticle Oil into the nail and surrounding skin. The oil will penetrate the nail and provide a protective cushioning within the nail itself to help prevent breakage.

